部署流程

① 安装miniconda

安装包下载

2 创建环境并切换

```
conda create --name occ python=3.8
conda activate occ
```

3 安装Python第三方库

```
conda install -c conda-forge pythonocc-core=7.5.1

pip install -r requirements.txt
```

requirements.txt:

```
PyQt5=5.15.11
cx_Freeze=7.2.0
setuptools=65.6.3
```

4 打包

python setup.py build

执行成功后,可执行程序在build目录下

⑤ 修改config.ini为可执行程序路径。例如

[Paths]

```
executablePath = ./exe.macosx-11.0-arm64-3.8/utils
```

6 修改CMakeLists.txt中Qt5路径并在build目录下执行编译链接命令:

```
cd build
cmake ..
make
```